


# TERRACE

Designed by Robert Kaufman Fabrics    Featuring  
[www.robertkaufman.com](http://www.robertkaufman.com)

**KONA**® ∞ COLOR  
cotton solids 01 OF THE  
2 YEAR



Finished quilt measures: 61" x 75-12"

**Pattern Level: Enthusiastic Novice**




**"I am a total beginner and want to learn more!"**

**ROBERTKAUFMAN**  
F A B R I C S

*For questions about this pattern, please email [Patterns@RobertKaufman.com](mailto:Patterns@RobertKaufman.com).*

## Fabric and Supplies Needed

*Fabric amounts based on yardage that is 42" wide.*

Color	Fabric	Name/SKU	Yardage	Color	Fabric	Name/SKU	Yardage
	A	K001-957 TIGERLILY	4 yards		Binding*	K001-957 TIGERLILY <i>*Also used for Fabric A</i>	5/8 yard
	B	K004-1242 NATURAL	1-1/2 yards	You will also need: 4 yards for backing			
Copyright 2017, Robert Kaufman For individual use only - Not for resale							

## Notes Before You Begin

- Read through all of the instructions before beginning.
- All of the seam allowances are 1/4" unless otherwise noted.
- Press seam allowances open unless otherwise noted.
- Width of fabric (WOF) is equal to at least 42" wide.
- Right sides together has been abbreviated to RST.
- Remember to measure twice and cut once!

## Cutting Instructions

### From Fabric A, cut:

two 18-1/2" x WOF strips. Subcut:

- nine 18-1/2" x 6-1/2" rectangles (C)
- one 18-1/2" x 3-3/4" rectangle (D)
- one 18-1/2" x 10-3/4" rectangle (E)

six 1-1/2" x WOF strips. Subcut:

- four 1-1/2" x WOF strips (F). Sew two strips together. Trim to create one 1-1/2" x 76" sashing strip. Repeat to make a second sashing strip.
- eight 1-1/2" x 5-1/2" rectangles (G)
- four 1-1/2" x 6-1/2" rectangles (H)

eight 2-1/2" x WOF strips. Subcut:

- four 2-1/2" x WOF strips (I). Sew two strips together. Trim to create one 2-1/2" x 76" border strip. Repeat to make a second border strip.
- one 2-1/2" x 9-3/4" rectangle (J)
- eleven 2-1/2" x 13-1/2" rectangles (K)

two 8-1/2" x WOF strips. Subcut:

- three 8-1/2" x 7-1/2" rectangles (L)
- one 8-1/2" x 16-3/4" rectangle (M)
- one 8-1/2" x 9-3/4" rectangle (N)
- one 8-1/2" x 10-3/4" rectangle (O)
- one 8-1/2" x 2-3/4" rectangle (P)
- one 8-1/2" x 3-3/4" rectangle (Q)

eight 6-1/2" x WOF strips. Subcut:

- thirty-nine 6-1/2" x 6-1/2" squares. Cut one TEMPLATE B from each square.
- two 6-1/2" x 6-1/2" squares (R)
- one 6-1/2" x 10-3/4" rectangle (S)
- one 6-1/2" x 9-3/4" rectangle (T)

one 3-3/4" x WOF strips. Subcut:

- one 3-3/4" x 12-1/2" rectangle (U)
- one 3-3/4" x 6-1/2" rectangle (V)

**From Fabric B, cut:**

four 6-1/2" x WOF strips. Subcut:

- twenty 6-1/2" x 7-1/2" rectangles. Cut two TEMPLATE A from each rectangle; there will be one extra.

twelve 1-1/2" x WOF strips. Subcut:

- eight 1-1/2" x 8-1/2" rectangles (W)
- sixteen 1-1/2" x 6-1/2" rectangles (X)
- four 1-1/2" x 27-1/2" rectangles (Y)
- four 1-1/2" x 19-1/2" rectangles (Z)
- eight 1-1/2" x 7-1/2" rectangles (AA)
- one 1-1/2" x 16-3/4" rectangle (BB)
- one 1-1/2" x 3-3/4" rectangle (CC)

In order to maximize the full WOF, cut larger strips lengths first, then cut smaller strips from the remaining lengths.

**From Binding Fabric, cut:**


seven 2-1/2" strips

## Sew the Curves

**Step 1:** Pair each TEMPLATE A foreground piece with its TEMPLATE B background piece.

**Step 2:** With right sides together, match the centers. Pin at the center close to the edge of the fabric. Align the edge of the TEMPLATE A with the edge of the TEMPLATE B piece. Pin at these end points. Pin at least one more time between the already placed pins. Repeat for each pair.

**Step 3:** Using a scant 1/4" seam allowance, stitch along the curve. At every pin, leave the needle in the DOWN position and raise your presser foot. Realign your edges and make sure everything is lining up. Lower your presser foot and remove that pin. Take it slow and carefully. Align the edges as you stitch.




**Step 4:** Move the sewn pair to your pressing board with the TEMPLATE A piece lying right side up. Push back the TEMPLATE B portion and use a seam roller or finger press the curved seam. With right sides still up, press the TEMPLATE B piece back so that the seam allowance remains behind the TEMPLATE B portion.

**Step 5:** Repeat for all thirty-nine AB units.

## Sew the ABX Units



**Step 1:** Place an AB unit on your table with the "B" portion in the upper right corner, sew an "X" piece to the bottom of fifteen AB units.

**Step 2:** With the "B" portion still in the upper right corner, sew an AB unit to the bottom of the fifteen ABX units from the previous step, as shown in the diagram overview, with the "B" portion in the lower right corner.




# Sew the First Two Columns

**Step 1:** Sew a "K" unit to the left side of seven the ABX units from the previous step, as shown.



**Step 2:** Sew the first column as shown.

**Step 3:** Sew the second column as shown.





## Sew the Rows for the Last Column

**Step 1:** Sew together a "Y", "G" and "AA" pieces as shown in the diagram overview. Repeat for a total of four YGAA units.



**Step 2:** Sew together a "Z", "G", "AA" and "H" pieces as shown in the QAD. Repeat for a total of four ZGAAH units.



**Step 3:** Place an ABX unit on your table with the "B" portions in the upper right and left corners. Sew an AB unit to the left side, as shown in the diagram overview, with the "B" portion in the lower right corner. Repeat for a total of four units. Sew a "C" piece on the right side of each unit. Repeat for all ABCX top four units.



**Step 4:** Place an ABX unit on your table with the "B" portions in the lower right and left corners. Sew an AB unit to the left side, as shown in the diagram overview, with the "B" portion in the upper right corner. Repeat for a total of four units. Sew a "C" piece on the right side of each unit. Repeat for all ABCX bottom four units.



**Step 5:** Sew together the "U", "CC", "V" and "D" pieces as shown in the QAD.

**Step 6:** Sew together the UCCVD unit with a ABXC top unit as shown in the QAD. Sew the "J" piece to the left side. Sew a YGAA unit to the bottom. This is ROW1.

**Step 7:** Sew together ABXC bottom, ZGAAH and ABXC top units as show in the QAD. Sew a "K" piece to the left side. Sew a YGAA unit to the bottom. Repeat for ROW2, ROW3 and ROW4.

**Step 8:** Sew together an AB unit, "R", "X", "R" and "C" pieces as shown in the QAD.

**Step 9:** Sew together an ABXC bottom, ABRXRC from the previous step and "C" as shown in the QAD. Sew "K" to the left side. This is ROW 5.

**Step 10:** Sew together the "X" and "T" pieces as shown in the QAD.

**Step 11:** Sew together the "O", "S", "BB", "XT" and "E" as shown in the diagram. This is ROW 6.

## Sew Column 3 and Finish the Quilt

**Step 1:** Sew together ROW1 through ROW6 as shown in the diagram. This is COLUMN 3.

**Step 2:** Sew together COLUMN 1, COLUMN 2, and COLUMN 3. Sew border "I" to the right side.

**Step 3:** Trim to 61" x 75-1/2".



Print at 100%.

Check size printed correctly using 1" box for scale prior to cutting fabric.  
Transfer the templates to template plastic if desired.

1" box for  
scale

**ROBERTKAUFMAN**  
F A B R I C S

**TERRACE**  
TEMPLATE A

**ROBERTKAUFMAN**  
F A B R I C S

**TERRACE**  
TEMPLATE B

This pattern may be used for personal purposes only and may not be reproduced in any form without the express permission from Robert Kaufman Fabrics. This pattern is not for resale. All patterns, unless otherwise attributed, are © Robert Kaufman Co., Inc. 2005-2017. All rights reserved.